Meritus Al

SCRATCH4PHIRO*

+ INSTALLATION GUIDE +



Scratch4Phiro Installation Guide

Welcome to the world of **Scratch4Phiro** , where you can bring your ideas to life and make the Phiro robot do amazing things!



This guide will help you install and setup **Scratch4Phiro** on a Windows computer. Follow these steps, and you'll be ready to create your very first program in no time. Let's dive into the fun of coding and robotics!



Coming soon for MacOS.

Step 1 - Check for Required Software

Before we get started, let's make sure your computer has the software needed to run Scratch4Phiro. Follow the steps below based on whether you're a new user or an existing user.

New User Steps:

- 1. Press **Windows key + R** on your keyboard at the same time.
 - This will open a small box called the **Run Command.**
- 2. In the box, type **appwiz.cpl** and then press **Enter.**
 - This will open a list of all the programs installed on your computer.
- 3. Check whether **Adobe AIR** and **Adobe Flash** applications are installed.
 - If they are not installed, proceed directly to STEP 2 App Installation Process. {Page 4}

Existing User Steps:

- 1. Press **Windows key + R** on your keyboard at the same time.
 - This will open a small box called the Run Command.
- In the box, type appwiz.cpl and then press Enter.
 - This will open a list of all the programs installed on your computer.
- 3. Look for **Adobe AIR** and **Adobe Flash** in the list.
- 4. The Scratch4Phiro app requires Adobe AIR software, **version 33.1.1.744.**
 - To maintain the required version, you must remove any other versions of Adobe AIR.
- 5. If Adobe AIR and Adobe Flash are installed:
 - Locate and double-click
 Uninstall_Adobe_AIR.exe (provided in the package).Here
 - Select Adobe AIR and Adobe Flash, then click Uninstall . (Refer to Image 1)




Image 1

Step 2 - Install Scratch4Phiro

Now it's time to install **Scratch4Phiro**:

- 1. Download the **Scratch4Phiro.exe** file from <u>here</u>.
 - o If you see a warning message, click **Keep File** to continue.
- 2. Open the downloaded **Scratch4Phiro.exe** file.
 - Follow the instructions on the screen to install the app.
- 3. During installation, **Adobe AIR version 33.1.1.744** will install automatically.
- 4. When installation is done, double-check that **Adobe AIR** was installed correctly:
 - Press Windows key + R, type appwiz.cpl, and press Enter.
 - Make sure **Adobe AIR version 33.1.1.744** is listed in the programs.

Meritus Al

Step 3 - Pairing Phiro with Software

Follow these steps to connect your **Phiro robot** to your computer using Bluetooth and link it with the **Scratch4Phiro app**:

Turn on Advanced Bluetooth Discovery:

- Go to Settings > Bluetooth & Devices > Devices > Device Settings > Bluetooth Device Discovery.
- Change the mode from **Default** to **Advanced.**






Image 2 Image 3

2. Turn on Phiro:

- Power on the Phiro robot and switch it to Bluetooth Mode . Add Phiro as a Bluetooth Device :(Refer to Image 2)
- Go to Settings > Bluetooth & Devices > Add a
 Device.
- Locate **Phiro's number** (found on the bottom of the Phiro bot).(Refer to Image 3)
- Select the device, and when prompted, enter the PIN:
 1234 to pair. (Refer to Image 4)



Image 4

4. Identify Phiro's Connection Port:

- Navigate to Bluetooth & Devices > Devices > More
 Bluetooth Settings > COM Ports.
- Note the port number listed as **Outgoing** (e.g., COM4).

5. **Connect Phiro to Scratch4Phiro:**

- Open the **Scratch4Phiro app.**
- Select the Outgoing COM Port you noted earlier and click the Connect button.(Refer to Image 5)
- In the Scratch4Phiro app , go to Scripts > More Blocks.
- A green circle indicator in the app and a green LED on the Phiro bot will confirm a successful connection. (Refer to Image 6)

6. **Connection Issues:**

- o If a **red circle** appears in the **Scratch4Phiro app** and the **green LED** on the Phiro bot does not glow, it means Phiro is disconnected. (*Refer to Image 7*)
- In that case, repeat the **Phiro Pairing Process** from the beginning.

Important: Each time you reconnect Phiro, you must follow the **Step 3** - Phiro Pairing Process again.



Image 5




Image 6



Image 7

Step 4 - Run your First Program

Ready to see your robot in action? Let's run a sample program:

- 1. Download a **Sample Program** from <u>here</u>.
- 2. Open **Scratch4Phiro.**
- 3. Click **File > Open**, then select a sample program you downloaded.
- 4. Click the **Flag icon** to start the program.
- 5. Watch as Phiro follows your commands!




Image 8

Step 5 - Troubleshooting Tips

Sometimes things don't go as planned. If Phiro isn't working, try these steps:

- If Phiro disconnects, go back and follow STEP 3 again.
- Make sure that:
 - Bluetooth is turned on.
 - You're using the correct COM Port.

Need help? email us at support@meritus.ai.

Have fun Creating, Coding and Exploring with Scratch4Phiro!

THANK YOU

Scan the QR Codes below to explore more using Phiro



Phiro Video



Phiro with Scratch & Pocket Code Video Playlist